

ComColor Technical Bulletin

1 Page 1
of 1

ISSUE NO. : CCT-034

MODEL: ComColor 90xx, 70xx & 30XX

DATE 09 April, 2010

Data Category Field Modification Trouble Shooting General Information Safety Advice

Proceeding Grade

- Action ASAP
 Action as given
 Action if required
 Refer in need

Parts Compatibility

- Compatible
 Conditionally Compatible
 Not Compatible
 Old Obsolete

Handling of Modified Parts

- Free of Charge
 Conditionally Chargeable
 Chargeable

Our Ref. C02580

SUBJECT: RISO Printer Driver (GDI) CD109V

[Brief]

The ComColor Printer Driver has been upgraded as follows.

1. RISO Printer Driver (GDI): CD109V

(For Windows 2000, Windows XP, Windows Vista, Windows 2000 Server & Windows Server 2003)

[Major Revision]

1. The following program bugs have been corrected.
 - 1) On PDF file printing, a part of image may be rotated.
 - 2) On printing of Word2003, it may not make a print and repeat a initialization.
2. Change image processing on Binding width area:
Image of Binding width area has been change from same base color of original to no base color.

[Note]

Please delete previous printer driver before installing the new driver as below:

1. Delete the icon of RISO ComColor on "Printers & Faxes".
2. Select "File"/ "Server Properties" and click "Drivers" tab and delete RISO ComColor.
3. Select "Start"/"All Programs"/"RISO" and click ComColor Uninstaller

Reboot the computer after upgrading printer driver to CD109V.

If you did not reboot it, a print job in spool holder will be locked on "Printing".

[Application Serial Number]

Will be informed later

CC9050	3335xxxx
CC7050	3336xxxx
CC3050	3337xxxx
CC7010	3346xxxx
CC3010	3347xxxx

Attached:

